



*For orders contact:*

**UK Sales Manager & N England**  
**Graeme Dalton**      **07789 486266**

**Scotland**  
**Simon Mellor**      **07790 372828**

**Wales and Southern England**  
**Aled Davies**      **07789 716884**

**Central England**  
**Maldwyn Davies**      **07721 892752**

**ANIMAX Limited**  
Shepherds Grove West,  
Stanton,  
Bury St Edmunds,  
Suffolk, IP31 2AR  
T: +44 (0)1359 252181  
F: +44 (0)1359 252182  
[www.animax-vet.com](http://www.animax-vet.com)

# paracide 62

**NEW** HIGH CONCENTRATION  
of our  
TIME PROVEN OP DIP

**10 litre and 5 litre packs**  
**give maximum economy**  
**for contractors and for**  
**flocks of all sizes**



## Paracide 62 Initial Dilution.

At a rate of 1 litre of Paracide 62 to 1500 litres of clean water. If your dip bath is calibrated in gallons you get 4.55 litres in 1 gallon (e.g. 22 gal = 100L)

BATH VOLUME LITRES	600	1200	2400	4800
VOLUME OF PARACIDE 62 TO ADD	400 ml	800 ml	1.60 litres	3.20 litres

## Paracide 62 Topping Up.

Top up after **20 sheep** at a rate of 1 litre of Paracide 62 to 1000 litres of clean water. If the volume of the dip bath drops by less than 50 litres after 20 sheep still add 50 ml of Paracide 62 and top up with water to the original level.

BATH LEVEL DROP IN LITRES	50	75	100	150	200	250
VOLUME OF PARACIDE 62 TO ADD	50ml	75ml	100ml	150ml	200ml	250ml



The following are examples of likely dip concentrate requirements for top ups, for May/June from sheep at 3 different stages of fleece growth, dipped in a 1,500 litre batch, topped up after every 20 sheep.

TIME OF DIPPING	DROP IN DIP BATH (EST.)	DIP CONCENTRATE REQUIRED	
		PARACIDE 62	COMPETITORS
SUMMER	50 litres	50 ml	100 ml
BACK END	75 litres	75 ml	100 ml
SPRING	100 litres	100 ml	100ml

Note: Dip wash should be changed at least daily, or after a number of sheep equivalent to:-

Initial Dip Bath Fill (litres) ÷ 2